

Version 7.5

Quick Start Guide

This guide is intended to help you get started with a base configuration for Lotus Sametime Enterprise Meeting Server.



National Language Version: To obtain the Quick Start Guide in other languages, print the PDF from the Quick Start CD.

Product overview

The Lotus Sametime Enterprise Meeting Server interoperates with Sametime servers to provide failover and load balancing functionality for a group of Sametime servers. The Enterprise Meeting Server ships separately from Sametime, but is not a standalone application and provides no functionality by itself.

1 Step 1: Access your software



If you download your product from Passport Advantage®, follow the directions in the download document: www.ibm.com/support/docview.wss?rs=477&uid=swg24012423

This product offering includes:

- **Quick Start CD (includes all supported language versions of this guide)**
- Sametime Enterprise Meeting Server 7.5 CD
- DB2 Universal Database™ Enterprise Server Edition 8.2 for Windows® CD
- WebSphere® Application Server 6.0 for Windows CD


2 Step 2: Evaluate your hardware and system configuration



Review the hardware and software requirements for Enterprise Meeting Server. When possible, use the recommended levels rather than the minimum levels to improve performance. See the detailed system requirements and other configuration information listed in the Sametime Enterprise Meeting Server 7.5 Release Notes at www.lotus.com/idd/doc

3 Step 3: Review the base architecture and installation steps

Enterprise Meeting Server is hosted on a WebSphere Application Server and interoperates with an LDAP directory server, a DB2® database server, and two or more Sametime servers.




4 Step 4: Access your documentation

 The following Sametime and Enterprise Meeting Server documentation is available:

- Sametime 7.5 Administrator's Guide, which includes product documentation for Enterprise Meeting Server, is available on Lotus developerWorks® at www.lotus.com/ldd/doc
- Sametime Enterprise Meeting Server 7.5 Release Notes are available on the Enterprise Meeting Server CD. The most up-to-date Release Notes are posted on developerWorks.

5 Step 5: Install and configure Enterprise Meeting Server

 Enterprise Meeting Server is hosted on WebSphere Application server, and must be installed after the LDAP directory, Sametime servers, and database management system with which it interoperates. The steps below provide an overview of tasks required to install and set up an Enterprise Meeting Server. For complete step-by-step installation instructions that address each of these procedures, see the Sametime 7.5 Administration Guide.

1. Install the LDAP directory server.
2. Install two or more Sametime 7.5 servers.
3. Install the DB2 database server.
4. Install and configure WebSphere Application Server on the computer that will host Enterprise Meeting Server.
5. Install Enterprise Meeting Server, and then create the Meeting Services and Community Services clusters.

If Enterprise Meeting Server is not hosted on the same computer as the DB2 server, install the DB2 Administration Client on the computer hosting Enterprise Meeting Server.

More information

 For additional technical resources, see:

- Lotus developerWorks at www.lotus.com/ldd/doc
- IBM Redbooks™ at www.redbooks.ibm.com

